

NAME

pdfjadetex – PDF output from JadeTeX

SYNOPSIS

pdfjadetex [*options*] [*commands*]

DESCRIPTION

This manual page was derived from the manual page for pdfTeX and is not meant to be exhaustive. The complete documentation for this version of TeX can be found in the info file or manual *Web2C: A TeX implementation*.

pdfjadeTeX is a version of TeX that can create *PDF* files as well as *DVI* files.

The typical use of pdfjadeTeX is with a pregenerated formats for which PDF output has been enabled. The **pdfjadetex** command uses the equivalent of the plain JadeTeX format.

pdfjadeTeX's handling of its command-line arguments is similar to that of L^ATeX.

OPTIONS

This version of pdfjadeTeX understands the following command line options.

--fmt *format*

Use *format* as the name of the format to be used, instead of the name by which pdfjadeTeX was called or a %& line.

--help Print help message and exit.**--ini** Be **pdfnitetex**, for dumping formats; this is implicitly true if the program is called as **pdfnitetex**.**--interaction** *mode*

Sets the interaction mode. The mode can be one of *batchmode*, *nonstopmode*, *scrollmode*, and *errorstopmode*. The meaning of these modes is the same as that of the corresponding \commands.

--ipc Send DVI or PDF output to a socket as well as the usual output file. Whether this option is available is the choice of the installer.**--ipc-start**

As **--ipc**, and starts the server at the other end as well. Whether this option is available is the choice of the installer.

--kpathsea-debug *bitmask*

Sets path searching debugging flags according to the bitmask. See the *Kpathsea* manual for details.

--maketex *fnt*

Enable mktex *fnt*, where *fnt* must be one of *tex* or *tfm*.

--no-maketex *fnt*

Disable mktex *fnt*, where *fnt* must be one of *tex* or *tfm*.

--output-comment *string*

Use *string* for the DVI file comment instead of the date.

--progname *name*

Pretend to be program *name*. This affects both the format used and the search paths.

--shell-escape

Enable the `\write18{command}` construct. The *command* can be any Bourne shell command. This construct is normally disallowed for security reasons.

--version

Print version information and exit.

ENVIRONMENT

See the Kpathsearch library documentation (the ‘Path specifications’ node) for precise details of how the environment variables are used. The **kpsewhich** utility can be used to query the values of the variables.

One caveat: In most pdfjadel^T_EX formats, you cannot use `~` in a filename you give directly to pdfjadel^T_EX, because `~` is an active character, and hence is expanded, not taken as part of the filename. Other programs, such as METAFONT, do not have this problem.

TEXMFOUTPUT

Normally, pdfjadel^T_EX puts its output files in the current directory. If any output file cannot be opened there, it tries to open it in the directory specified in the environment variable TEXMFOUTPUT. There is no default value for that variable. For example, if you say *tex paper* and the current directory is not writable, if TEXMFOUTPUT has the value */tmp*, pdfjadel^T_EX attempts to create */tmp/paper.log* (and */tmp/paper.pdf*, if any output is produced.)

TEXINPUTS

Search path for `\input` and `\openin` files. This should probably start with “.”, so that user files are found before system files.

TEXFONTS

Search path for font metric (*.tfm*) files.

TEXFORMATS

Search path for format files.

TEXPOOL

search path for **pdfnitetex** internal strings.

TEXEDIT

Command template for switching to editor. The default, usually **vi**, is set when pdfjadel^T_EX is compiled.

FILES

The location of the files mentioned below varies from system to system. Use the **kpsewhich** utility to find their locations.

pdfjadetex.pool

Encoded text of pdfjadel^T_EX’s messages.

texfonts.map

Filename mapping definitions.

**.tfm* Metric files for pdfjadel^T_EX’s fonts.

**.fmt* Predigested pdfjadel^T_EX format (*.fmt*) files.

BUGS

This version of pdfjade_T_EX fails to trap arithmetic overflow when dimensions are added or subtracted. Cases where this occurs are rare, but when it does the generated *DVI* file will be invalid.

SEE ALSO

jadetex(1), **tex(1)**, **mf(1)**, **undump(1)**.

AUTHORS

The author of pdfjade_T_EX is Sebastian Rahtz.

This manual page was derived by Marcus Brinkmann for the Debian distribution from the pdf_T_EX manual page from the te_T_EX distribution by Thomas Esser.